





1 Hour Project Clutches

The Caroline Clutch pattern shows a fresh new way to create the bag corners that give the clutch its volume, and the oversized button decoration complements the cute character of the bag.



The Caroline Clutch

This darling little bag tucks perfectly into your palm. Its tiny size is great if you're looking to carry only a few items such as your cell phone and wallet, and as a result, it is ideal for use as a makeup

THE CAROLINE CLUTCH

FINISHED SIZE: 6 ½" WIDTH X 5" HEIGHT X 2" DEPTH

This darling little bag tucks perfectly into your palm. Its tiny size is great if you're looking to carry only a few items such as your cell phone and wallet, and as a result, it is ideal for use as a makeup bag or glasses carrier. This clutch may also be used as a Nintendo case. The Caroline Clutch pattern shows a fresh new way to create the bag corners that give the clutch its volume, and the oversized button decoration complements the cute character of the bag. The bonus of this bag's decoration is that you get the cuteness of the button without the hassle of actually having to use it when opening or closing the clutch. Everybody needs a cute little clutch or two. Why not start on one now? *Designer's Review*

MATERIAL LIST

FABRIC

44" wide heavyweight home decorator OR quilting weight cotton
(1/8) Yard for exterior fabric
(1/8) Yard for lining

OTHERS

(1) 18mm Magnetic Snap
(1) Spool of coordinating thread
(1) 2" Button (Optional)

INTERFACING (Optional)

(1/8) Yard of 44" wide medium weight fusible interfacing

TOOL LIST

Ruler, Scissors, Chalk pencil, Pencil, Sewing machine, Pins, Needle, Shape tool

* Seam allowance 1/4" unless otherwise specified.

* All units are in inches.

Cut out the Fabric

Draw the patterns directly onto the wrong side of a single layer of fabric. Cut out the exterior, lining, and interfacing, and fuse the interfacing on the wrong side of the exterior front and back pieces following the manufacturer's guide.

EXTERIOR

(2) Front and Back Pieces

(1) Flap

INTERIOR

(2) Lining Front and Back Pieces

(1) Lining Flap Piece

INTERFACING

(2) Front and Back Pieces

(1) Flap Piece

Apply the magnetic snap


Attach the magnetic snap onto the right side of the lining flap and exterior front piece following the manufacturer's guide. Center the snap onto the interfacing and use a pencil to draw a line where the fabric will be cut. Cut the line. Insert the prongs of one of the magnetic snaps into the right side of the exterior front. Secure the thin prongs on the wrong side of the exterior front. Punch the hole only onto the lining flap piece. Assemble the flap, and then attach the other magnetic snap in the same manner.

Sew the Exterior

Place the exterior front and back pieces with right sides together. Pin and sew the exterior, backstitching on both ends, sew the 3 sides as shown in **Picture 1**.

Make the Corners

Draw a 1" x 1" square on each bottom corner of the exterior fabric's wrong side, **see Picture 2**. Flip the fabric onto its side and pinch each bottom corner so that the corner seam forms a triangle and the 1" mark forms a straight line, **see Picture 3**. Pin and sew following the line, **see Picture 4**.



Picture 1



Picture 2



Picture 3



Picture 4

Trim the corner seams, *see Picture 5*. Sew the lining in the same manner, leaving a 4" gap for turning, *see Picture 6*.



Picture 5



Picture 6

Construct the Flap

Place the flap lining and exterior with right sides together. Pin and stitch together, backstitching on both ends, *see Picture 7*. Clip the curved seams, *see Picture 8*. Turn the flap right side out, press and topstitch, *see Picture 9*. Position the flap on the exterior back piece, right sides together. Pin and baste the flap and the bag, backstitching on both ends, *see Picture 10*.



Picture 7



Picture 8



Picture 9



Picture 10

Assemble the Exterior and Lining

Turn the exterior right side out and tuck it into the lining with right sides together, *see Picture 11*. The flap should be sandwiched between the exterior and lining. Pin and sew around the top opening, backstitching on the start and end points, *see Picture 12*. Turn the bag right side out through the opening. Stitch the opening closed, *see Picture 13*. Tuck the lining into the exterior. Press the top opening of the clutch and topstitch across the top, *see Picture 14*. For decoration, sew a button onto the center edge of the flap.



Picture 11



Picture 12



Picture 13



Picture 14


© 2009 Copyright of ithinksew.com

Only if you follow these conditions will I allow you to sell the finished products. *Give full credit to ithinksew.com for the patterns (this applies online and offline) For example, when you're selling one of my patterns online include a sentence like this: "This pattern was designed by ithinksew.com". A link to my shop would also be really appreciated. When selling the patterns offline, write this on the tag. * The finished products may only be made by crafters. It may not be mass produced. * The conditions above may change



THE CAROLINE CLUTCH Front and Back Panel

1/4 - inch seam allowance *included*
Exterior fabric: Cut 2
Lining: Cut 2
Interfacing: Cut 2





PDF PATTERN & MORE


THE CAROLINE CLUTCH Flap


¼ - inch seam allowance *Included*

Exterior fabric: Cut 1

Lining: Cut 1

Interfacing: Cut 1





** When printing this pattern, please print it without any margins at actual size.

** After printing the pattern and taping the pieces together, please follow the reference the provided size guide (3" or 5").

** Patterns marked as A4 are for users who utilize the A4 standard paper size.

** If you experience that certain parts of the pattern are not printing, you should be able to ignore those near the edge/border. These are usually just guides & signs.